

# INTERLAB

Tel: +331 3971 7337 – Fax: +331 3928 9008

## ISSUE: Setting up Shared Projects In Lightworks V10

Concerned platforms: New LW 10.0.x

Vernouillet, 11.10.2010

## Setting up Shared Projects In Lightworks

Below are the steps required for setting up a shared media space and shared project spaces.

On both Lightworks machines map the required network drives ie, map one drive for the Projects (P:\) and one for the Media (M:) either using Editshare connect or Windows. **Please Note: Both machines must have the same drive letters mapped for project sharing to work.**

### Managing Project Spaces

You will need to assign the newly created networks drives to the Project Space and the Media location (This needs to be done on all Lightworks machines)

- On the Lightworks Project Browser click the cogs icon in the top right to open the menu
- Click Manage project spaces..
- Click the drop down arrow next to "Location"
- Select the mapped drive to be used for the location of the shared project ie, P:\ and click Do it
- Click the drop down arrow next to "Default material location"
- Select the mapped drive to be used for the Media ie, M:\ and click Do it

### Creating a Project Space

Next you need to create the new Project Space (This only needs to be done once on one of the Lightworks machines. Once it has been created it will be available to select on the other Lightworks machines)

- Click the "New project space" button
- Enter a name for the project space (this is basically the folder where all the project files will be kept) and click Do it

# INTERLAB

Tel: +331 3971 7337 – Fax: +331 3928 9008

- You can add additional material locations should they be required by clicking "Add" and selecting other drives/folders
- Close the "Manage project space" menu or create additional Project Spaces by repeating the instructions above

## Choosing the Project Space

Once the project space has been set up it can be selected from the Project Browser

- Click the drop down arrow at the top of the Project Browser next to "Local Projects"
- Select the newly created project space
- Create a project as you would do normally

## Creating Additional Rooms

Once the project has been created, additional rooms will need to be created for multiple users to enter the same project

- On the projects browser, click the screen grab of the selected project.
- The list of rooms available will appear
- Click "New room"

## Windows 7 64bit

On Windows 7 64bit systems with multiple network adaptors it is necessary to control which adaptor the broadcast messages are sent on. (It appears to send on only one adaptor which is different behaviour to Windows XP). To configure this you need to add a Lightworks registry entry (String Value) in HKLM\Software\WOW6432Node\Lightworks\Configuration - "Adaptor IP". Simply enter the configured static IP of the adaptor to be used.

Thanks Mat.

Pls. send us your feel back. Rev.1 – David 31. 07.2011